

FreeRADIUS

WNAM 1.5 FreeRADIUS-.

 WNAM 1.6 .
WNAM Linux iptables/ipset, UniFi TP-LINK EAP RADIUS- , , FreeRADIUS .

FreeRADIUS

FreeRADIUS :

```
apt-get install freeradius
```

 FreeRADIUS 2.. 3. . 3.
, FreeRADIUS /etc/raddb/, - /etc/freeradius/.

FreeRADIUS Perl-, /etc/freeradius/3.0/sites-enabled/, wnam-freeradius-bridge.pl /etc/freeradius/3.0/. , [http://www.netams.com/files/wnam/misc/freeradius2 freeradius3](http://www.netams.com/files/wnam/misc/freeradius2%20freeradius3), , .

		,
wnam-freeradius-bridge.pl	/etc/freeradius/3.0/	(FreeRADIUS WNAM)
clients.conf	/etc/freeradius/3.0/	(IP-) RADIUS- (), (), RADIUS-
default	/etc/freeradius/3.0/sites-available	(WNAM)
perl	/etc/freeradius/3.0/mods-available	(perl- wnam-freeradius-bridge.pl)
wnam.properties	/etc	, ,

FreeRADIUS 3.0 :

- /etc/freeradius/3.0/mods-enabled/perl -> /etc/freeradius/3.0/mods-available/perl /etc/freeradius/3.0/sites-enabled/default -> /etc/freeradius/3.0/sites-available/default :

```
ln -s /etc/freeradius/3.0/mods-available/perl /etc/freeradius/3.0/mods-enabled/perl
ln -s /etc/freeradius/3.0/sites-available/default /etc/freeradius/3.0/sites-enabled/default
```

- /etc/freeradius/3.0/mods-enabled/eap EAP- /etc/freeradius/3.0/sites-enabled/inner-tunnel :

```
rm -f /etc/freeradius/3.0/sites-enabled/inner-tunnel /etc/freeradius/3.0/mods-enabled/eap
```

 /etc/freeradius/3.0/clients.conf , RADIUS- , .

freeradius :

```
service freeradius restart
```

, FreeRADIUS X , - () .